SEND EVENT SEND EVENT

SEND EVENT

Note:

This statement is only available under Windows.

SEND EVENT operand1 TO [DIALOG-ID]
$$\begin{cases} operand2 \\ * DIALOG-ID \end{cases}$$

$$\begin{bmatrix} \left\{ \begin{aligned} \mathbf{WITH} & \left\{ operand3 \begin{bmatrix} (\mathbf{AD} = \begin{pmatrix} \mathbf{M} \\ \mathbf{O} \\ \mathbf{A} \end{bmatrix} \right\} \\ n\mathbf{X} \end{aligned} \right\} \end{bmatrix} \\ \mathbf{USING} & [\mathbf{DIALOG}] & (dialog-name) \end{aligned}$$
WITH PARAMETERS-clause $\begin{bmatrix} \mathbf{M} \\ \mathbf{O} \\ \mathbf{A} \end{bmatrix} \end{bmatrix}$

Operand	Possible Structure								Po	ssi	ble	Fo	rn	ats	S			Referencing Permitted	Dynamic Definition
Operand1	С	S				A												yes	no
Operand2		S							Ι									yes	no
Operand3	С	S	A			Α	N	P	Ι	F	В	D	T	L	С	G	О	yes	no

Function

You use this statement to trigger a user-defined event within a Natural application.

Operands

Operand1 is the name of the event to be sent.

Operand2 is the identifier of the dialog receiving the user event. Operand2 must be defined with format/length I4.

AD=

If operand3 is a variable, you can mark it in one of the following ways:

AD=O	Non-modifiable, see Session Parameter AD=O.
AD=M	Modifiable, see Session Parameter AD=M.
	This is the default setting.
AD=A	Input only, see Session Parameter AD=A.

Copyright Software AG 2003

Operand3 cannot be explicitly specified if operand3 is a constant. AD=O always applies to constants.

Passing Parameters to the Dialog

It is possible to pass parameters to the dialog.

As operand3 you specify the parameter(s) to be passed to the dialog.

With the PARAMETERS-clause, parameters may be passed selectively.

nX

With the notation nX you can specify that the next n parameters are to be skipped (for example, 1X to skip the next parameter, or 3X to skip the next three parameters); this means that for the next n parameters no values are passed to the dialog.

A parameter that is to be skipped must be defined with the keyword OPTIONAL in the dialog's DEFINE DATA PARAMETER statement. OPTIONAL means that a value can - but need not - be passed from the invoking object to such a parameter.

PARAMETERS-clause

PARAMETERS {parameter-name = operand3}... END-PARAMETERS

Notes

You can only use the PARAMETERS-clause if the specified target dialog (dialog-name) is cataloged.

Dialog-name is the name of the dialog receiving the user event.

Note

If the value of a parameter marked with AD=O and passed "by reference" is changed in a dialog, this will lead to a runtime error.

Further Information and Examples

See the section Event-Driven Programming Techniques in the Natural Programming Guide.